



Cold Process Shaving Soap

Recipe makes approximately 6 heaped shaving soaps.

Here's What You Need:
Ingredients

[Lye](#)
[COCONUT Oil-76](#)
[SHEA BUTTER](#)
[CASTOR Oil- 16 oz.](#)
[Lanolin OIL USP Liquid](#)
[PALM Oil](#)
[APRICOT KERNEL Oil- 16 oz.](#)
[OLIVE Oil- Pomace](#)
[Bentonite Clay Powder](#)
[Black Code Type Fragrance Oil](#)
[SODIUM LACTATE - 16 oz.](#)
[Basic Circle- Mold Market Molds](#)
[8 oz. BLACK LOW PROFILE Jar & Lid SET](#)
[Safety Glasses for Soap Making](#)
[Safety GLOVES for Soap Making- 1 pair](#)
[Safety MASK for Soap Making- 2 count](#)
[THERMOMETER](#)

Other Ingredients & Equipment You'll Need:

Water
Scale
Mixing Spoon
Spatula
Stick Blender
Mixing bowls



Here's How It's Done : Directions

Total Recipe Weights:

- 259 grams Water
- 94 grams Lye
- 42 grams Sodium Lactate (added to the cooled lye solution)

- 170 grams Coconut Oil 76
- 170 grams Palm Oil
- 54 grams Castor Oil
- 34 grams Lanolin Oil Liquid
- 82 grams Apricot Kernel Oil
- 102 grams Olive Oil Pomace
- 68 grams Shea Butter
- 14 grams Bentonite Clay Powder
- 42 grams Black Code Type Fragrance Oil

Clean & Sanitize your work area and all of your packaging materials. It is suggested that you wear gloves, protective clothing, a face mask, safety glasses, and a hair net while preparing this recipe.

[Click Here For Basic CP Soap Making Class](#). Also, before attempting to make any cold process soap, please become familiar with [Soap Making Safety Class](#).

Please Note: The Sodium Lactate is added to the lye solution once it has cooled.

For this recipe, you will want to add the Bentonite Clay Powder to the soap batter when it is at emulsion. Then, stick blend to incorporate. You will have to use a spatula to scrap the walls of the mixing bowl to ensure all of the Bentonite clay is incorporated for a smooth finish in your soaps. When the soap is at trace and you are ready to pour, simply fill the basic circles. Then, carefully tap the mold to release any air bubbles. Next, heap the tops of the mold with the remaining batter. Unmold after 24 hours. (You may have to stick the molds in the freezer before popping the soaps out.) Once the soap has cured, place one circle into each 8oz low profile jar and lid.

Natures Garden is not responsible for the performance of any of the recipes provided on our website. Testing is your responsibility. If you plan to resell any recipes we provide, it is your responsibility to adhere to all FDA regulations. If there are ingredients listed in a recipe that Natures Garden does not sell, we cannot offer any advice on where to purchase those ingredients.

We hope that you enjoy our Cold Process Shaving Soap recipe!